

Sample Preparation

1. Measure 2 level measuring spoons (30 ml) full of dry soil into the soil sample cup.
2. Add 2 (30 ml) measuring spoons of the soil extractant to the soil.
3. Mix the soil and the solution by stirring with the spoon for at least 2 minutes, making sure the soil sample is thoroughly mixed. Let stand for 5 minutes
4. Fold a circular filter in half 'twice' and open it up to form a cone. Place it in the soil suspension as far as possible. The filtration will take place from the outside of the filter to the inside.
5. As soon as sufficient filtrate accumulates in the filter, use the small pipette to transfer the soil extract onto the sensor of the LAQUA meter.
6. Read the value from the digital display after it has stabilized (30 - 45 sec.). Subtract 34 from the display value. This accounts for the 34 ppm NO_3^- in the extractant solution. For lbs/acre, multiply by 4 for a sampling depth of 12 inches. Note: For soils very low in nitrate, it is possible to get sensor readings less than 34.
7. Rinse sensor and blot dry. Display should read close to "0" with distilled water on it, if not rinse again.

PREPARING SOIL-LESS MEDIA

Sample collection

1. Collect sample just before plants are irrigated.
2. Avoid the top layer of media with no roots.
3. Collect root media from the bottom $\frac{2}{3}$ of the pot.
4. Take samples from 10 or more plants distributed in the sample population.
5. When a sufficient amount of root media is collected, mix the sample.

Sample Preparation and Analysis

1:2 Extraction method

Measure a known volume of root media in a beaker or cup (usually 50 to 100 ml or $\frac{1}{4}$ to $\frac{1}{2}$ cup). Fill firmly so it is compressed as it was in the pot. Be consistent when measuring. DO NOT lightly fill or heavily pack the beaker. Place the sample into a cup or beaker.

Add 2 equal volumes of distilled water into the cup, mix the sample and wait 10 minutes. Measure the nitrate after sieving out the large particles. The nitrate level can be read directly from the slurry.

Saturated media extract method

Place 300 to 500 ml (1 to 2 cups) of root media sample in a cup or beaker.

Slowly add distilled water, constantly stirring the sample with a spatula or knife. Add enough distilled water so that the sample behaves like a paste with the surface glistening with water, but with no free water on the surface of the sample.

After 15 minutes, add more water if needed.

Extract the solution from the media using a pipette, Buchner funnel, side arm, flask and vacuum pump, filter bag or sieve. Make any additional measurements (such as EC) using the extracted solution. Table 2 gives a general idea of the nitrate levels to look for in the extracted solution.

| Media Type | ppm NO₃⁻-N in extract |
|---|--|
| Seedlings | 40 - 70 |
| Young pot and foliage plants | 50 - 90 |
| Pot and bedding plants-growing on | 80 - 160 |
| Roses, mums or snapdragons in ground or raised beds | 120 - 200 |
| Lettuce and tomatoes in ground beds | 125 - 225 |
| Celery transplants | 75 - 125 |

Table 2: Interpretation of Greenhouse Soils: Desirable NO₃⁻-N concentrations in saturated media extract.

COLLECTING TISSUE SAP

When conducting a test on plant materials, the biggest source of error is due to sampling. This error results when a sample is not representative of the source. Follow these steps to gather and care for your sample:

- 1.) Do not sample plants which show obvious signs of nutrient deficiency or damage from disease, insects, or chemicals unless these plants are the subject of a study. Plants which have been under stress for a period of time may not give a true picture of the nutrient status of the field.
- 2.) The leaves or parts of leaves selected should be of the same age and relative position on the plant. The most recently matured leaves should be used. These are the leaves that have stopped expanding in size. The petiole or leaf stem of the leaf or appropriated plant material should be used for the test.
- 3.) A minimum of 25 petioles or leaves should be collected. This is enough to represent a five to ten acre field if the field is judged to be uniform. Chop up the petioles and mix and sub-sample these pieces for testing. Crops with small, dry petioles, such as strawberries require much larger samples to get enough sap compared to fleshy crops such as tomatoes. Store whole petioles, not leaves, at room temperature for up to 1½ hours or on ice for up to eight hours. Cold petioles should be warmed to room temperature before taking a measurement.
- 4.) Depending on how succulent the petiole is, use a handheld or hydraulic plant sap press (p. 29) to squeeze sap from the petioles.

**PETIOLE NO₃-N SUFFICIENCY LEVELS
FOR DRIP-IRRIGATED VEGETABLES**
(SOURCE: UC-DAVIS)

| Crop | Growth Stage | Petiole NO ₃ -N concentration | |
|----------------------------|-----------------------|--|-------------|
| | | Dry Tissue | Fresh Sap |
| Broccoli | Mid growth | 10,000 - 20,000 | 1000 - 1600 |
| | Button formation | 8000 - 15,000 | 800 - 1200 |
| | Preharvest | 5000 - 8000 | 600 - 1000 |
| Cabbage | Cupping | * | 1200 - 1500 |
| | Early heading | * | 1000 - 1200 |
| | Mid heading | * | 700 - 900 |
| Canteloupe | Early flower | 12,000 - 15,000 | 1000 - 1600 |
| | Fruit bulking | 8000 - 10,000 | 800 - 1000 |
| | First harvest | 4000 - 6000 | 700 - 800 |
| Cauliflower | Mid growth | * | 1000 - 1600 |
| | Curd development | * | 700 - 1000 |
| | Preharvest | * | 500 - 800 |
| Celery | Mid growth | 7000 - 10,000 | 600 - 800 |
| | Preharvest | 6000 - 10,000 | 400 - 600 |
| Lettuce | Early head formation | 7000 - 10,000 | 400 - 600 |
| | Preharvest | 6000 - 8000 | 300 - 500 |
| Onion | Bulbs 0.5-1.5 in. | * | 350 - 500 |
| Pepper | Vegetative growth | 7000 - 10,000 | 900 - 1200 |
| | Early flower/fruit | 5000 - 8000 | 700 - 1000 |
| | Fruit bulking | 5000 - 8000 | 700 - 1000 |
| | Preharvest | 5000 - 7000 | 700 - 900 |
| Potato (Russet Burbank) | Early vegetative | 17,000 - 22,000 | 1300 - 1600 |
| | Mid tuber/bulking | 11,000 - 15,000 | 900 - 1200 |
| | Late tuber/maturation | 6000 - 8000 | 550 - 700 |
| Sweet Corn | Entire season | * | 600 - 700 |
| Tomato | Vegetative growth | 10,000 - 14,000 | 700 - 900 |
| | Early flower/fruit | 9000 - 12,000 | 600 - 800 |
| | Fruit bulking | 6000 - 8000 | 500 - 700 |
| | Preharvest | 4000 - 7000 | 400 - 600 |
| Watermelon | Early flower | 12,000 - 15,000 | 1000 - 1600 |
| | Fruit bulking | 8000 - 15,000 | 700 - 900 |
| | Fruit harvest | 5000 - 8000 | 500 - 700 |

PETIOLE NO₃-N SUFFICIENCY LEVELS

(SOURCE: UNIVERSITY OF FLORIDA)

| Crop | Growth Stage | NO ₃ -N (ppm) Fresh Sap |
|------------------------|-----------------------------|---------------------------------------|
| Cucumber | First blossom | 800 - 1000 |
| | Fruits 3-inches long | 600 - 800 |
| | First harvest | 400 - 600 |
| Broccoli & Collards | Six-leaf stage | 800 - 1000 |
| | Just prior to harvest | 500 - 800 |
| | At first harvest | 300 - 500 |
| Summer Squash | First blossom | 900 - 1000 |
| | First harvest | 800 - 900 |
| Muskmelon | First blossom | 1000 - 1200 |
| | Fruits 2-inches long | 800 - 1000 |
| | First harvest | 700 - 800 |
| Tomato (field) | First buds | 1000 - 1200 |
| | First open flowers | 600 - 800 |
| | Fruit 1-inch diameter | 400 - 600 |
| | Fruit 2-inch diameter | 400 - 600 |
| | First harvest | 300 - 400 |
| | Second harvest | 200 - 400 |
| Bell Pepper | First flower buds | 1400 - 1600 |
| | First open flowers | 1400 - 1600 |
| | Fruits half-growth | 1200 - 1400 |
| | First harvest | 800 - 1000 |
| | Second harvest | 500 - 800 |
| Eggplant | First fruit (2-inches long) | 1200 - 1600 |
| | First harvest | 1000 - 1200 |
| | Mid harvest | 800 - 1000 |
| Potatoes | Plants 8-inch tall | 1200 - 1400 |
| | First open flowers | 1000 - 1400 |
| | 50% of flowers open | 1000 - 1200 |
| | 100% of flowers open | 900 - 1200 |
| | Tops falling over | 600 - 900 |

PETIOLE NO₃⁻-N SUFFICIENCY LEVELS (CONT.)

(SOURCE: UNIVERSITY OF FLORIDA)

| Crop | Growth Stage | NO₃⁻-N (ppm) Fresh Sap |
|-----------------------|---------------------|---|
| Annual Hill | November | 800 - 900 |
| Strawberries | December | 600 - 800 |
| (October planting) | January | 600 - 800 |
| | February | 300 - 500 |
| | March | 200 - 500 |
| | April | 200 - 500 |
| Watermelon | Vines 6-inches long | 1200 - 1500 |
| | Fruit 2-inches long | 1000 - 1200 |
| | Fruits half mature | 800 - 1000 |
| | First harvest | 600 - 800 |

PETIOLE NO₃⁻-N SUFFICIENCY LEVELS FOR POTATOES
(SOURCE: UNIV. WISCONSIN-MADISON)

Optimum range of nitrate-nitrogen concentrations (dry weight and sap basis) in potato petiole at various stages of growth

| Growth Stage (days after emergence) | Norkotah, Norland, Atlantic, Kennebec | Shepody, R. Burbank, Snowden | Onaway Superior |
|---|--|------------------------------------|--------------------|
| dae | Dry Weight Basis (% NO₃⁻-N) | | |
| 30 | 2.5 - 2.8 | 2.0 - 2.3 | 2.3 - 2.5 |
| 40 | 2.3 - 2.5 | 1.7 - 2.2 | 2.0 - 2.3 |
| 50 | 1.8 - 2.3 | 1.2 - 1.6 | 1.5 - 1.9 |
| 60 | 1.3 - 1.9 | 0.8 - 1.1 | 0.9 - 1.2 |
| 70 | 0.8 - 1.1 | 0.5 - 0.8 | 0.4 - 0.6 |
| | Sap Basis (ppm NO₃⁻-N) | | |
| 30 | 1900 - 2100 | 1600 - 1800 | 1800 - 1900 |
| 40 | 1800 - 2000 | 1600 - 1700 | 1600 - 1800 |
| 50 | 1400 - 1800 | 1000 - 1300 | 1200 - 1500 |
| 60 | 1110 - 1500 | 700 - 900 | 500 - 1000 |
| 70 | 700 - 900 | 500 - 700 | 400 - 600 |

Values from the LAQUA can be converted to dry tissue calibration by using the equation:

$$\% \text{Dry Weight NO}_3^- \text{-N} = 0.00142 (\text{ppm sap NO}_3^- \text{-N}) - 0.21$$

PETIOLE NO₃⁻-N SUFFICIENCY LEVELS RUSSET BUR-
BANK POTATOES
(SOURCE: UNIV. OF MINNESOTA)

| Growth Stage | Petiole NO ₃ ⁻ -N (ppm) | |
|-------------------------------|---|-------------|
| | Dry Tissue | Fresh Sap |
| Early Vegetative/tuberization | 17,000 - 22,000 | 1300 - 1600 |
| Mid tuber growth/bulking | 11,000 - 15,000 | 900 - 1600 |
| Late tuber growth/maturation | 6,000 - 8,000 | 550 - 700 |

PETIOLE NO₃-N SUFFICIENCY LEVELS

(SOURCE: MICHIGAN STATE UNIVERSITY)

The following guidelines are based on one year's research results and will be revised as necessary based on future research findings. Readings taken on youngest fully extended petiole.

Carrots

Adequate petiole sap nitrate concentration

| Carrot shoulder diameter (in.) | Nitrate-N (ppm) | Nitrate (ppm) |
|--------------------------------|-----------------|---------------|
| Prior to sizing | 750+ | 3,300+ |
| 0.00 - 0.25 | 550+ | 2,420+ |
| 0.25 - 0.50 | 450+ | 1,980+ |
| 0.50 - 0.75 | 300+ | 1,320+ |
| 0.75 - 1.50 | 250+ | 1,100+ |
| > 1.50 | 200+ | 880+ |

Celery

Adequate petiole sap nitrate concentration

| Weeks after transplant | Nitrate-N (ppm) | Nitrate (ppm) |
|------------------------|-----------------|---------------|
| 0 - 5 | 800+ | 3,520+ |
| 5 - 6 | 725+ | 3,190+ |
| 6 - 7 | 650+ | 2,860+ |
| 7 - 8 | 575+ | 2,530+ |
| 8 - 9 | 500+ | 2,200+ |
| 9 - 10 | 425+ | 1,870+ |
| 10 - 11 | 350+ | 1,540+ |
| 11+ | 275+ | 1,210+ |

Onions

Adequate petiole sap nitrate concentration

| Growth Stage | Nitrate-N (ppm) | Nitrate (ppm) |
|-----------------|-----------------|---------------|
| Up to 5 leaves | 800+ | 2,520+ |
| 5 to leaves | 600+ | 2,640+ |
| Bulb initiation | 300+ | 1,320+ |
| Bulb bulking | 250+ | 1,110+ |

PRE-SIDEDRESS NITRATE (PSNT) SOIL TEST INTERPRETATION

University of Tennessee

| | |
|---------|---|
| <17 | ppm NO ₃ ⁻ -N Low |
| 17 - 25 | ppm NO ₃ ⁻ -N Low |
| >25 | ppm NO ₃ ⁻ -N Low |

Rutgers Cooperative Extension

| PSNT Soil Test Level (ppm NO ₃ ⁻ -N) | Sidedress N Recommendation |
|---|-------------------------------|
| 1 - 15 | 160 |
| 16 - 20 | 120 |
| 21 - 25 | 80 |
| 26 - 30 | 40 |
| 31+ | 0 |

University of Wisconsin

| PSNT result (ppm N) | Soil Potential* | |
|---------------------|---|------------|
| | Very High/High N/application Rate (lbs/Acre) | Medium/Low |
| <10 | 160 | 120 |
| 11 - 12 | 150 | 80 |
| 13 - 14 | 125 | 80 |
| 15 - 17 | 100 | 40 |
| 18 - 20 | 60 | 40 |
| >21 | 0 | 0 |

* consult WMEX pub. A2809

Pennsylvania Nitrogen Soil Test Recommendation (Lbs N/Acre)

(Source: Penn State University)

| Soil Test Level (ppm NO ₃ ⁻ -N) | Corn Yield Goal | | | | |
|--|-----------------|-----|-----|-----|-----|
| | 100 | 125 | 150 | 175 | 200 |
| 0 - 10 | 100 | 130 | 160 | 190 | 220 |
| 11 - 15 | 75 | 100 | 125 | 150 | 150 |
| 16 - 20 | 50 | 75 | 100 | 125 | 125 |
| 21 - 25 | 25 | 50 | 75 | 100 | 100 |
| 25+ | 0 | 0 | 0 | 0 | 0 |

Note: Check you county extension office for updates